

# iConvert for Perceptive Content

## Product Guide

Version: Foundation EP4

Written by: Product Knowledge, R&D  
Date: April 2022

# Copyright

Information in this document is subject to change without notice. The software described in this document is furnished only under a separate license agreement and may be used or copied only according to the terms of such agreement. It is against the law to copy the software except as specifically allowed in the license agreement. This document or accompanying materials contains certain information which is confidential information of Hyland Software, Inc. and its affiliates, and which is subject to the confidentiality provisions agreed to by you.

All data, names, and formats used in this document's examples are fictitious unless noted otherwise. Complying with all applicable copyright laws is the responsibility of the user. Without limiting the rights under copyright law, no part of this document may be reproduced, stored in or introduced into a retrieval system, or transmitted in any form or by any means (electronic, mechanical, photocopying, recording, or otherwise), or for any purpose, without the express written permission of Hyland Software, Inc. or one of its affiliates.

Hyland® and Hyland Software®, as well as Hyland product names, are registered and/or unregistered trademarks of Hyland Software, Inc. and its affiliates in the United States and other countries. All other trademarks, service marks, trade names and products of other companies are the property of their respective owners.

© 2022 Hyland Software, Inc. and its affiliates. All rights reserved.

## Table of Contents

<b>Copyright .....</b>	<b>2</b>
<b>What is iConvert? .....</b>	<b>4</b>
<b>Prepare a target database .....</b>	<b>4</b>
Database Collation .....	4
Database Recovery Model .....	4
Max Degree of Parallelism .....	4
Temporary Database .....	5
<b>Install iConvert .....</b>	<b>5</b>
Download the iConvert files .....	5
Verify remote Perceptive Content shared directory access .....	5
Prepare Perceptive Content Server .....	5
Perform an attended installation of iConvert .....	5
Run iConvert .....	6
View conversion progress .....	7
<b>After the conversion .....</b>	<b>7</b>
Review the event log .....	7
Address an INVALID status row .....	7
Address FAILED tables .....	7
Run the IN_EXTERN_MSG_SEQ.sql script .....	8
Uninstall iConvert and verify database connection .....	8
<b>Appendix A: Configuration files .....</b>	<b>8</b>
inserverConvert.ini .....	8

## What is iConvert?

iConvert is a Windows only multi-threaded utility that converts an Perceptive Content database from one DBMS to another. It can also convert your SQL Server database from ANSI to Unicode. The iConvert utility creates your tables and copies the data, then adds indexes and constraints for you. After you install it, you can run iConvert and monitor its progress using log files, which you can configure to receive automatically by email.

You can install iConvert as a manual or automatic service. If you install iConvert as an automatic service, iConvert will start each time you start the machine it is installed on. We recommend that you contact Perceptive Software support before beginning a database conversion.

## Prepare a target database

To prepare a target database, complete the following steps.

Complete one of the following steps to prepare the target database for conversion.

- If you are converting to Oracle, you must create the database instance before running iConvert. Refer to the appropriate Perceptive Content Server installation guide for additional information.
- If you are converting to Microsoft SQL, you must create the database shell, users, and privileges before starting iConvert by running the iConvert\_SQLServer-DBOnly.sql script, which is included in the installer.
- If you are converting to PostgreSQL, you must create the database shell, users, and privileges before starting iConvert by running the iConvert\_PostgreSQL-DBOnly.sql script, which is included in the installer.

**Note** You do not need to create the database tables or add indexes and constraints.

- If your ODBC connection is named Perceptive Content, stop all Perceptive Content services, then rename the existing ODBC connection to prevent it from being used as your target database. Create a new DSN named Perceptive Content for your destination database. The iConvert installer uses a connection for your target database with the default name of Perceptive Content.

## Database Collation

If migrating to Unicode, you must select the appropriate Unicode collation during the database creation and before you start the iConvert process.

## Database Recovery Model

Before starting the iConvert process, ensure that the destination database is using the Simple Recovery Model to ensure minimal logging and faster throughput. Once the iConvert process has finished, switch the Recovery Model to Full, perform a full database backup, and enable all of your standard database maintenance jobs.

## Max Degree of Parallelism

For the duration of the iConvert process, consider setting the Max Degree of Parallelism (MAXDOP) to a value that is appropriate on the hosting server in order increase processing capacity and reduce the overall duration of the conversion. After the iConvert process has finished, you can switch the MAXDOP

back to 1 to disable parallelism. For best practices, refer to Microsoft documentation and knowledge base articles.

## Temporary Database

Ensure that the TEMPDB database has a sufficient number of database files that are already sized appropriately to provide enough space for sorting in the tempdb during the iConvert process. For TEMPDB configuration best practices, refer to Microsoft documentation and knowledge base articles.

## Install iConvert

Prior to installing iConvert, verify that the source database schema matches the version of iConvert that you are using. To install iConvert, complete the following steps.

## Download the iConvert files

To obtain Perceptive product installation files, contact the Hyland Software Technical Support group. For a list of Technical Support phone numbers, go to [hyland.com/pswtscontact](http://hyland.com/pswtscontact).

## Verify remote Perceptive Content shared directory access

When the installer accesses a remote location it accesses the location in both the current user and SYSTEM context. You must verify both users have access to the shared directory. You can use the **net use** command to create sessions in the current context. You can also create a session in the SYSTEM context by using Microsoft's **Psexec** command to run the **net use** command in the SYSTEM context.

**Note** The **net use** command only adds the session for the current context. **Psexec** allows you to run the command in the SYSTEM context, which then adds the session in the SYSTEM context.

## Prepare Perceptive Content Server

1. Stop all Perceptive Content services.
1. Perform a complete backup of your Perceptive Content Server and database.
2. Verify that the existing database schema version matches the iConvert version.

## Perform an attended installation of iConvert

1. Double-click the downloaded **iConvertSetup\_[version].exe** file.
2. On the **Welcome to the Installation Wizard for ImageNow iConvert** page, click **Next**.
3. On the **License Agreement** page, review the License Agreement terms, scroll to the end of the agreement, click the **I accept the terms in the license agreement** button, and then click **Next**.
4. On the **Destination Folder** page, you may change locations for **ImageNow iConvert** and the **ImageNow iConvert shared files** using the following substeps.
  1. To change the location for the **ImageNow iConvert**, click **Browse**. In the **Change Current Destination Folder** page, browse to the destination folder where you want to install **ImageNow iConvert** and then click **OK**.
  2. To change the location for **ImageNow iConvert shared files**, click **Browse**. In the **Change Current Destination Folder** page, browse to the destination folder where you want to install the **ImageNow iConvert shared files** and then click **OK**.

5. On the **Destination Folder** page, click **Next**.
6. On the **Configure Source Perceptive Content Database** page, configure the Perceptive Content Database settings using the following substeps.
  1. Select the **Database type**.
  2. Specify the **Data Source Name (DSN)**.
  3. Enter the **Username** and **Password** for the **Database credentials**.
  4. Click **Verify** and review the ODBC driver configuration.
7. On the **Configure Source Perceptive Content Database** page, click **Next**.  
On the **Configure Destination Perceptive Content Database** page, configure the Perceptive Content Database settings using the following substeps.
  1. Select the **Database type**.
  2. Specify the **Data Source Name (DSN)**.
  3. Enter the **Username** and **Password** for the **Database credentials**.
  4. Click **Verify** and review the ODBC driver configuration.
8. On the **Configure Destination Perceptive Content Database** page, click **Next**.
9. On the **Email Notification** page, to configure iConvert to send email messages containing progress updates of the conversion, select **Check to configure email notification** and complete the following substeps and then click **Next**. Otherwise, click **Next** and continue to the next step.
  - In the **SMTP Server** field, specify the SMTP server you want iConvert to use to send email updates.
  - In the **SMTP Port** field, specify the port number of SMTP Server.
  - In the **Send to address** field, specify the email address to which you want iConvert to send email updates.
  - In the **Send from address** field, specify the email address from which you want iConvert to send email updates.
10. On the **Email Notification** page, click **Next**.
11. On the **Ready to Install the Program** page, click **Install**.
12. On the **Installation Wizard Completed** page, click **Finish**.

## Run iConvert

1. Stop all Perceptive Content services.
2. Make sure all sessions are closed by verifying the IN\_SC\_SESSION table is empty in the source database.
3. In an Administrator **Command Prompt** window, navigate to the Perceptive Content local bin64 directory **\$(IMAGENLOWLOCALDIR6)\bin64** and type **inserverConvert -start** to start iConvert.

**Note** If you stop and restart iConvert, the conversion process begins where it left off. If you installed iConvert as a manual service, you must complete the previous step to re-start the process.

## View conversion progress

To view your conversion progress, complete the following steps.

1. Navigate to Perceptive Content local log directory `$(IMAGENLOWLOCALDIR6)\log` and, in a browser, open the **convertresult.htm** file.
2. Each row represents the conversion process of an ODBC table. If the row is green, the conversion completed successfully. Yellow indicates the conversion is in progress. White or gray indicates the table has not yet started conversion. Red indicates the table did not convert successfully.

**Note** Some rows may turn red temporarily during the conversion.

## After the conversion

The iConvert conversion is complete when the service is stopped and the process is no longer running. After iConvert completes the conversion, you need to review the event log for failed tables, update the licenses, and remove the iConvert utility.

## Review the event log

You can view the convertresult.htm file and review the status log from your conversion. This highlights ODBC tables that did not convert successfully. Address entries in the event log that are either highlighted in red or have an INVALID status. To review the event log, complete the following steps.

1. Navigate to the Perceptive Content local log directory `$(IMAGENLOWLOCALDIR6)\log`.
2. In a browser, open the convertresult.htm file to view the status log. Review the log for FAILED or INVALID statuses and complete one of the following options.
  - If all statuses are SUCCESSFUL, proceed to run the **IN\_EXTERN\_MSG\_SEQ.sql** script.
  - If there are INVALID statuses, proceed to address failed tables.

**Note** This generally resolves any errors concerning indexes or constraints. Review the event log again after restarting.

## Address an INVALID status row

An INVALID status row indicates that the import was successful, however there were errors adding indexes or constraints. To troubleshoot INVALID status rows, complete the following steps.

1. In an Administrator **Command Prompt** window, navigate to Perceptive Content local bin64 directory `$(IMAGENLOWLOCALDIR6)\bin64` and type **inserverConvert -start** to rerun iConvert.

**Note** This generally resolves any errors concerning indexes or constraints.
2. Review the event log. If the INVALID rows still exist, complete the following substeps.
  1. In the source database, look for items that break the foreign key constraint.
  2. Fix any of these occurrences.

## Address FAILED tables

A FAILED status indicates that the table did not import successfully. To troubleshoot FAILED tables, complete the following steps.

1. In an Administrator **Command Prompt** window, navigate to the Perceptive Content local bin64 directory `$(IMAGENLOWLOCALDIR6)\bin64`, then type **inserverConvert -scrub-table <table name>**, which scrubs individual tables in the Database.
2. Run the **-scrub-table** command for all failing tables.
3. In a **Command Prompt** window, type **inserverConvert -start** to begin the rerun conversion of the failed tables.
4. Verify that the tables are no longer FAILED. For any remaining failing tables, rerun the command.

**Note** This action truncates the records from the tables and sets their statuses to “not started”.

**Note** You may need to run this command several times for each table.

## Run the IN\_EXTERN\_MSG\_SEQ.sql script

To complete the conversion of your SQL Server database, you must run the IN\_EXTERN\_MSG\_SEQ.sql script. This script will copy the data in the inemuser.IN\_EXTERN\_MSG\_SEQ table from the existing server (source\_db) to the new server (dest\_db). This process only applies to SQL Server databases. To prepare and execute the script, complete the following steps.

1. In **SQL Server Management Studio**, connect to the Unicode server using a login with system administrator privileges.
2. Open the **IN\_EXTERN\_MSG\_SEQ.sql** script and complete the following substeps.
3. Ensure the variables in the Variable Declaration section of the script are set to the correct source, destination server, and database for your environment.
4. Replace the **INOW6\_DESTINATION** variable name with the name of the destination Unicode database.
5. **Note** This name must match the declared **v\_dest\_db** variable.
6. Click **Execute**.

**Note** This script creates a temporary linked server between the two instances of SQL Server in order to pull data between the source and destination databases.

## Uninstall iConvert and verify database connection

Upon completing your database conversion, it is recommended that you uninstall iConvert and verify your Perceptive Content Server database connection. To perform these actions, complete the following steps.

1. Following your operating system's steps for removing programs, uninstall iConvert.
2. On each machine with a Perceptive Content service that connects directly to the database, ensure that the ODBC settings in the inow.ini are configured according to your new database.

## Appendix A: Configuration files

### inserverConvert.ini

The following table provides definitions and sample data for the settings in the inserverConvert.ini configuration file. This table displays the INI settings under group headings in brackets, for example, [General]; in the order the groups appear in the INI file. Each setting offers two or more options, which are



defined in the table below along with a description of each setting and its options. Use this table as a guide when customizing the file.

Section	Setting	Options	Description
General	num.workers	Any positive integer	Specifies the number of worker threads in the main pool. The default is 15.
	throttle.threshold	Any positive integer	Specifies the maximum number of inserts iConvert allows before committing the open transaction. The default is 1000.
	retry.attempts	Any positive integer	Specifies the number of times iConvert attempts the insert. The default is 3.
Logging	debug.level.file	0 through 6	Specifies the level iConvert uses to log errors for troubleshooting. 0 = Logging is off. 1 = The least verbose logging. 6 = The most verbose logging. The default is 0.
	socket.level.file	0, 1	Specifies whether to log communication between Perceptive Content Server and iConvert. 1 = iConvert logs communication. 0 = iConvert does not log communication. The default is 0.
	status.log.interval		Specifies how often, in seconds, iConvert refreshes the ConvertResult.html log file. The default is 10.
ODBC	src.dbms	SQLServer, Oracle, PostgreSQL	Specifies the source DBMS the customer is converting from.
ODBC (continued)	src.dsn	Any valid database name	Specifies the source database name.
	src.user.id	Any valid user ID	Specifies the user ID for the source ODBC connection.

Section	Setting	Options	Description
	src.user.password	A valid password	Specifies the password that is consumed by the application for encryption in the <b>src.user.password.encrypted</b> setting. This value is encrypted and removed from the setting after running the <code>insererConvert -encrypt-config</code> command. The default is <code>imagenow</code> .
	src.user.password.encrypted		Specifies the encrypted password for the source database that is maintained by the application.
	dest.dbms	SQLServer, SQLServerUnicode, Oracle, PostgreSQL	Specifies the destination DBMS to which the customer is converting.
	dest.dsn	Any valid database name	Specifies the destination database name.
	dest.user.id	Any valid user ID	Specifies the user ID for the destination ODBC connection.
	dest.user.password	A valid password	Specifies the password that is consumed by the application for encryption in the <b>dest.user.password.encrypted</b> setting. This value is encrypted and removed from the setting after running the <code>inserverConvert -encrypt-config</code> command. The default is <code>imagenow</code> .
	dest.user.password.encrypted		Specifies the encrypted password for the destination database that is maintained by the application.
Email	smtp.server	Any valid IP address or server name of an SMTP server	Specifies the SMTP server iConvert uses to email <code>convertresult.htm</code> .
	smtp.port	Any existing port number	Specifies the port number of SMTP Server.
	email.to	Any email address	Specifies the email address to which iConvert sends emails containing the <code>convertresult.htm</code> log file.
	email.from	Any email address	Specifies the email address from which iConvert sends emails containing the <code>convertresult.htm</code> log file.

