

Perceptive Intelligent Capture

Hot Patch Release Notes

Version: 5.6 SP2 Build 5651

Written by: Product Knowledge, R&D

Date: September 2016

© 2016 Lexmark. All rights reserved.

Lexmark is a trademark of Lexmark International Inc., registered in the U.S. and/or other countries. All other trademarks are the property of their respective owners. No part of this publication may be reproduced, stored, or transmitted in any form without the prior written permission of Lexmark.

Table of Contents

Overview	4
<i>Update</i>	<i>4</i>
Install the service pack	4
Uninstall the service pack	5

Overview

This document describes a defect corrections and installation instructions for hot patch build 5651 for Perceptive Intelligent Capture (PIC) 5.6 SP2.

Update

This hot patch includes the following update.

- Resolved an issue in Verifier where the initial manual extraction to a table cell may fail (TFS 11845).

Install the service pack

To install this hot patch, complete the following steps.

1. Stop or exit the following services and applications.
 - Runtime Server instances and Runtime Server services
 - Designer instances
 - Verifier instances
2. Back up the contents of the following directory, including subdirectories.
 - **[installation directory]\Components\Cedar**
3. Extract the files from the hot patch package.
4. Copy the contents of the extracted Cedar directory to the following directory, overwriting the existing files, if any.
 - **[installation directory]\Components\Cedar**
5. As an administrator, register the components with the following batch file.
 - **[installation directory]\Components\Cedar\RegCdr.bat**
6. Review the registration log to verify that all components are registered.
7. Restart the Runtime Server instances and services.
8. Restart the Designer and Verifier instances.

9. Monitor the log.

Uninstall the service pack

To uninstall this hot patch, complete the following steps.

1. Stop or exit the following services and applications.
 - Runtime Server instances and Runtime Server services
 - Designer instances
 - Verifier instances
2. Restore the following directory, including subdirectories.
 - **[installation directory]\Components\Cedar**
3. As an administrator, register the components with the following batch file.
 - **[installation directory]\Components\Cedar\RegCdr.bat**
4. Review the registration log to verify that all components are registered.
5. Restart the Runtime Server instances and services.
6. Restart the Designer and Verifier instances.