

Titan

Installation and Setup Guide

Version: 3.0.x

Written by: Documentation Team, R&D
Date: November 2023

Documentation Notice

Information in this document is subject to change without notice. The software described in this document is furnished only under a separate license agreement and may only be used or copied according to the terms of such agreement. It is against the law to copy the software except as specifically allowed in the license agreement. This document or accompanying materials may contain certain information which is confidential information of Hyland Software, Inc. and its affiliates, and which may be subject to the confidentiality provisions agreed to by you.

Complying with all applicable copyright laws is the responsibility of the user. Without limiting the rights under copyright law, no part of this document may be reproduced, stored in or introduced into a retrieval system, or transmitted in any form or by any means (electronic, mechanical, photocopying, recording, or otherwise), or for any purpose, without the express written permission of Hyland Software, Inc. or one of its affiliates.

Hyland, HXP, OnBase, Alfresco, Nuxeo, and product names are registered and/or unregistered trademarks of Hyland Software, Inc. and its affiliates in the United States and other countries. All other trademarks, service marks, trade names and products of other companies are the property of their respective owners.

© 2023 Hyland Software, Inc. and its affiliates.

The information in this document may contain technology as defined by the Export Administration Regulations (EAR) and could be subject to the Export Control Laws of the U.S. Government including for the EAR and trade and economic sanctions maintained by the Office of Foreign Assets Control as well as the export controls laws of your entity's local jurisdiction. Transfer of such technology by any means to a foreign person, whether in the United States or abroad, could require export licensing or other approval from the U.S. Government and the export authority of your entity's jurisdiction. You are responsible for ensuring that you have any required approvals prior to export.

Table of Contents

Documentation Notice	2
Overview	5
Prerequisites	5
Titan	5
Secure Environment Recommendations.....	5
Side-Channel Risks.....	5
Download.....	6
Install	6
Configure	7
<i>Configure app.config.json</i>	7
<i>Configure integrationserver.ini</i>	7
Appendix A: Token authentication	8
Appendix B: app.config.json file	8
appInfo	8
inactivityTimeoutInMinutes	8
authConfig	8
loginSubtitle	9
loginLogoUrl.....	9
displayModules	9
appSettings.....	9
<i>general</i>	10
<i>integrationServer</i>	10
<i>documentViewer</i>	10
<i>formViewer</i>	10
<i>propertiesPane</i>	11
<i>renderingConversionService</i>	11
<i>search</i>	12
<i>documentPrinter</i>	12
exportEmail.....	12
<i>to</i>	12
<i>cc</i>	12
<i>bcc</i>	13
<i>subject</i>	13

<i>preBody</i>	13
<i>postBody</i>	13
capture	13
<i>fileMaxFileSize</i>	13
<i>toolkitDownloadLocation</i>	13
<i>postSaveScriptName</i>	13

Overview

This document explains how to download and deploy Titan.

Prerequisites

The following prerequisites are required prior to installing Titan.

- Perceptive Content Integration Server and Apache Tomcat. For more information, refer to the [Perceptive Integration Server on Tomcat Installation Guide](#).
- **Note** If using Forms with Titan, Titan must reside on the same server as Integration Server.
- OpenID Connect Compatible Identity Provider - Any OIDC provider including [Hyland Identity Provider](#).
- Hyland Preferences Service
- Perceptive Content Rendering and Conversion Service

Titan

Secure Environment Recommendations

The following recommendations are intended to help secure the installation environment and apply to all product installations. These recommendations should be followed as a minimum requirement for all Hyland products. The policies of your organization may have additional or more robust requirements that should also be followed.

Hyland products may have additional recommendations described in the specific documentation for that product. In some cases, the recommendations may change or may only apply when using certain Hyland products together in a solution.

- Use TLS for all HTTP traffic, including private network segments. TLS ciphers have to be maintained to stay current over time.
- Use Secure FTP instead of standard FTP for all FTP traffic.
- End-to-end encryption is recommended for all data in transport, independent of a network segment. Note that some regulatory compliance requirements may require end-to-end encryption.
- Change all default passwords before activation of the production system. This applies to Hyland products as well as third-party products used by Hyland products (such as a database server).
- Authorization rules should be configured and tested before activation of the production system. This applies to Hyland products as well as to file system folders and database user accounts.
- Use database encryption for all sensitive data persisted in the database.
- Use file system encryption for all sensitive data and content persisted on the file system.
- Enable encryption when available as part of a subsystem configuration. For example, since ODBC provides the capability to use strong encryption for data, it is recommended to have that option enabled.

Side-Channel Risks

Consider the following to mitigate side-channel risks:

- Ensure the latest application and operating system patches are applied.
- Ensure the latest firmware patches are applied for any hardware on-premises.

Download

To download Perceptive product installation files, complete the following steps.

1. Go to the Hyland Community site.
2. From the menu, click **Support** and then under **Software Downloads** select **Perceptive Downloads**.
3. Find and download the installer file corresponding to the version to be installed.

Note New and updated documentation and help topics are regularly published to the documentation website at docs.hyland.com.

Install

To install Titan, complete the following steps.

1. After downloading the *application* zip file to a temporary directory on your computer, create a subdirectory in the **webapps** directory of the Tomcat server. You may name the subdirectory with any name. We recommend using **titan**, which is used in the examples of this document.

Note The default location for the *webapps* directory is **[drive:]\Program Files\Apache Software Foundation\[Tomcat Installation]\webapps**.

2. Extract the files to the subdirectory you just created.
3. Navigate to the **Tomcat\conf** directory and open the **server.xml** file in a text editor.
4. In the **Host** section, add the **RewriteValve** following the example below.

```
<Host name="localhost" appBase="webapps" unpackWARs="true" autoDeploy="true">
    ... insert the following line anywhere in this Host tag ...
    <Valve className="org.apache.catalina.valves.rewrite.RewriteValve" />
</Host>
```

5. Save the **server.xml** file and close the text editor.
6. Navigate to the **Tomcat\conf\Catalina\localhost** directory, create a **rewrite.config** configuration file, and then open it in a text editor.
7. Add the following two lines, where **titan** is the name of the subdirectory you created in step 1.

```
RewriteCond %{REQUEST_PATH} !-f
RewriteRule ^/titan/(.*) /titan/index.html
```

Note If you already have Titan deployed in this Tomcat instance then this file will already have one or more entries. You must re-add both lines for the new subdirectory name.

8. Save the **rewrite.config** file and close the text editor.
9. Restart Tomcat.
10. Navigate to the **Titan \webapps\titan** directory.
11. Open the **index.html** file in a text editor.
12. Update the **<base href="/">** tag in line 3 to include the subdirectory name you used in step 1. You must include the leading and trailing forward slashes.

```
<!DOCTYPE html><html lang="en"><head>
```

```
<meta charset="utf-8">
<base href="/titan/">
```

13. Save the **index.html** file and close the text editor.

Configure

This section details the configuration process for Titan.

Configure app.config.json

To configure the app.config.json configuration file, complete the following steps.

1. Navigate to the assets directory and open the **app.config.json** configuration file in a text editor.

Note The default location for the configuration file is **[drive:] \Program Files\Apache Software Foundation\Tomcat 9.0\webapps\titan\assets**.

2. In the **authConfig** section, configure the following subsections.
 1. Set the appropriate values, where **<app-host>** specifies the application host you configured in the installation steps.

```
"authConfig": {
  "issuer": "https://<idp-host>/identityprovider",
  "clientId": "titan-app",
  "scope": "openid profile profile.onbase",
  "redirectUri": "https://<app-host>/view/authentication-confirmation",
  "postLogoutRedirectUri": "https://titan/home",
  "requireHttps": true
},
```

2. Update the **integrationServer.url** and **integrationServer.bearerLoginProfileName** settings to specify the host location for Integration Server and the bearer token login profile name.

```
"integrationServer": {
  "url": "https://<is-host>/integrationserver",
  "applicationId": "titan",
  "bearerLoginProfileName": ""
},
```

3. Update the **renderingConversionService.url** setting to specify the host location of the Perceptive Content Rendering and Conversion Service.

```
"renderingConversionService": {
  "url": "https://<rccs-host>:<port>"
},
```

3. Save the **app.config.json** configuration file and close the text editor.
4. Restart Tomcat.

Configure integrationserver.ini

To configure the integrationserver.ini configuration file, complete the following steps.

1. Navigate to the **[path]/\${TOMCAT_HOME}/webapps/integrationserver/WEB-INF** folder.
2. Open the **integrationserver.ini** configuration file in a text editor.
3. In the **[Forms]** section, set **forms.allowed.origins** to the appropriate application origin URL.
4. Save the **integrationserver.ini** configuration file and close the text editor.

Appendix A: Token authentication

A token signing key is required to configure Titan for agent token authentication or Integration Server bearer token authentication. Refer to the Token authentication chapter in the Manage Content help for more information. To configure a token signing key, complete the following steps.

1. In a text editor, open the **inow.ini** configuration file.
2. Under the **[Logon Control]** section, set `token.signing.key.path` to the file path of the private key used to sign tokens. If the private key is encrypted, set `token.signing.key.password` to the private key password. The token signing key must be in Base64 encoded DER (PEM) format.
3. In the same section, set the `token.signing.algorithm` to the algorithm used when signing tokens. Refer to inow.ini configuration file documentation for a list of supported values.
4. Import the certificate or public key associated with the configured private key using either the `import-cert` or the `import-public-key` **intool** commands, specifying `token-auth` for the SSO type. Refer to the **intool** documentation for more information.

Appendix B: app.config.json file

You can configure Titan by updating the app.config.json file. The following is a list of the sections available in the app.config.json file.

appInfo

The appInfo section specifies the application information for Titan.

name

Specifies the name of the product.

logoUrl

Specifies the path to the logo that displays when logging into Titan.

licenseUrl

Specifies the path to the license text file for Titan.

```
"appInfo": {
  "name": "Titan",
  "logoUrl": "assets/logo.svg",
  "licensesUrl": "assets/licenses.txt"
},
```

inactivityTimeoutInMinutes

The inactivityTimeoutInMinutes section specifies the amount of inactivity time, in minutes, that you want the system to wait before logging the user out of Titan.

```
"inactivityTimeoutInMinutes": 30,
```

authConfig

The authConfig section specifies the configuration options for validating Titan authentication.

issuer

Specifies the full URL to the Hyland IDP instance.

clientId

Specifies the clientId defined when configuring IDP.

scope

Specifies the list of scopes to request when connecting to the Identity Provider.

redirectUri

Specifies the URI to redirect to after authenticating with IDP.

postLogoutRedirectUri

Specifies the logout URI to redirect users to after logging out of Titan.

requireHttps

Specifies whether you want Titan to require https level authentication.

```
" authConfig": {  
  "issuer": "https://<idp-host>/identityprovider",  
  "clientId": "titan-app",  
  "scope": "openid profile",  
  "redirectUri": "https://<app-host>/<subdirectory>",  
  "postLogoutRedirectUri": "https://<app-host>/<subdirectory>",  
  "requireHttps": true  
},
```

loginSubtitle

The loginSubtitle section specifies the message that displays in the login dialog box.

```
"loginSubtitle": "Click login to begin the login process through the identity  
provider",
```

loginLogoUrl

The loginLogoUrl section specifies the URL location for the logo that displays on the login dialog box.

```
"loginLogoUrl": "assets/logo.svg",
```

displayModules

The displayModules section specifies which Titan modules to display on the application's home page.

```
"displayModules": {  
  "capture": true,  
  "documents": true,  
  "workflow": true  
},
```

appSettings

The appSettings section specifies the configuration options for the Titan application. The subsections are described below.

general

The general section specifies the general configuration settings for Titan.

pathDelimiter

Specifies the character used to separate values in the path that displays the folder location.

```
"general": {  
  "pathDelimiter": "\\\"  
},
```

integrationServer

The integrationServer section specifies the configuration options for Integration Server.

url

Specifies the URL for Integration Server.

applicationId

Specifies the application ID that Titan uses for the Hyland Preferences Service.

bearerLoginProfileName

Specifies the bearer token login profile name.

```
"integrationServer": {  
  "url": "https://<is-host>/integrationserver",  
  "applicationId": "titan",  
  "bearerLoginProfileName": ""  
},
```

documentViewer

The documentViewer section specifies the configuration options for the Document Viewer in Titan.

removeFormsPane

Removes the Forms pane from the viewer.

removePropertiesPane

Removes the Properties pane from the viewer.

useNativePdfViewer

Specifies whether to use your systems native PDF viewer to view PDF documents.

```
"documentViewer": {  
  "removeFormsPane": false,  
  "removePropertiesPane": false,  
  "useNativePdfViewer": false  
},
```

formViewer

The formViewer section specifies the configuration options for the Forms Viewer in Titan.

autoloadFirstForm

Specifies whether the first form in the list displays by default when viewing the Forms pane.

```
"formViewer": {
  "autoloadFirstForm": false
},
```

propertiesPane

The propertiesPane section specifies the configuration options for the Properties pane in Titan.

name

Specifies the display of the Name field in the Properties panes.

location

Specifies the display of the Drawer or Path field in the Properties panes.

keys

Specifies the display of the Field1 through Field5 fields in the Properties pane.

type

Specifies the display of the Type field in the Properties panes.

notes

Specifies the display of the Notes pane in the user interface.

customProperties

Specifies the display of the Custom Properties pane in the user interface.

pageLabel

Specifies the display of the page label in the user interface.

additionalPageMetadata

Specifies the display of additional page metadata under Page Properties on the Properties pane in the user interface.

```
"propertiesPane": {
  "displaySettings": {
    "document": {
      "name": "enabled",
      "location": "enabled",
      "keys": "enabled",
      "type": "enabled",
      "notes": "enabled",
      "customProperties": "enabled",
      "pageProperties": "disabled",
      "pageLabel": "disabled",
      "additionalPageMetadata": "disabled"
    }
  }
},
```

renderingConversionService

The renderingConversionService section specifies the host location for the Perceptive Content Rendering and Conversion Service.

```
"renderingConversionService": {
  "url": "https://<rccs-host>"
}
```

```
},
```

search

The search section specifies the configuration options for the search functionality in Titan.

vslExtendedOperatorsEnabled

Specifies whether Titan adds the “contains” and “ends with” operators in the list of search operators.

vslAnyKeyConditionEnabled

Specifies whether Titan includes the *Any Document Key* condition in the list of search conditions.

```
"search": {
  "vslExtendedOperatorsEnabled": true,
  "vslAnyKeyConditionEnabled": true
},
```

documentPrinter

The documentPrinter section specifies the configuration options for the printer settings in Titan.

pageSize

Specifies the paper size printed.

enableCoverPage

Specifies if the cover page of a document is to be printed.

enableAnnotations

Specifies if the annotations are printed.

```
"documentPrinter": {
  "pageSize": "Letter",
  "enableCoverPage": true,
  "enableAnnotations": true
}
```

exportEmail

The exportEmail section specifies whether the user can email links to a document and what values are included in the email template.

to

Specifies the email address of the recipient.

cc

Specifies a carbon copy of an email when the user wants to include someone other than the direct recipient.

bcc

Specifies a blind carbon copy of an email when the user does not want the other recipients to see who else is included in the email.

subject

Specifies a subject of an email where the user can add a short description of the main content.

preBody

Specifies the section where the user can add any content before a document or a workflow item link.

postBody

Specifies the section on complimentary closure, such as “Thanks & regards”.

```
"exportEmail": {
  "document": {
    "to": "to_recipient@domain.com",
    "cc": "cc_recipient@domain.com",
    "bcc": "bcc_recipient@domain.com",
    "subject": "Perceptive Content Document",
    "preBody": "Below are links to the documents:",
    "postBody": "Regards,"
  },
  "workflow": {
    "to": "to_recipient@domain.com",
    "cc": "cc_recipient@domain.com",
    "bcc": "bcc_recipient@domain.com",
    "subject": "Perceptive Content Workflow Item",
    "preBody": "Below are links to the workflow items:",
    "postBody": "Regards,"
  }
}
```

capture

The capture section specifies the settings for the Titan capture module.

fileMaxFileSize

Specifies the maximum file size, in MB, that you can upload when capturing a document. If the value is left blank then there is no maximum size limit.

toolkitDownloadLocation

Specifies the URL of where to download the Perceptive Web Scan Toolkit installer if the toolkit is not detected.

postSaveScriptName

Specifies the post-save iScript file.

```
capture: {
  fileMaxFileSize: "5",
  toolkitDownloadLocation: "http://127.0.0.1:8090/cloud/PerceptiveWebCapture.zip",
}
```

```
    postSaveScriptName: "post-save-actions.js"  
  };
```